

## HOWNER\_OPERATOR2

<b>English Name</b>	<b>EPA Handler ID (Primary Key)</b>																		
<b>Description</b>	Unique RCRA identification number assigned by the implementing State or Region to each RCRA site (e.g., generators; transporters; and treatment, storage, disposal facilities).																		
<b>Data Type and Length</b>	CHAR (12)																		
<b>Allowed Values</b>	Valid ID as outlined below:  The ID can be a minimum of 4 characters and a maximum of 12 characters.  The first two characters must be a valid state postal code which corresponds to the state in which the handler is located.  Spaces are not allowed.																		
<b>Default Value</b>																			
<b>Notes</b>	Handlers associated with Navajo Nation should be assigned Handler IDs beginning with "NN" regardless of where the handler is physically located.																		
<b>English Name</b>	<b>Activity Location (Primary Key)</b>																		
<b>Description</b>	Indicates the location of the agency regulating the handler.																		
<b>Data Type and Length</b>	CHAR (2)																		
<b>Allowed Values</b>	State postal code																		
<b>Default Value</b>	Location associated with the current user ID.																		
<b>Notes</b>	For a list of valid state postal codes, refer to the Table Column Information Report for LU_STATE.																		
<b>English Name</b>	<b>Source Type (Primary Key)</b>																		
<b>Description</b>	Code indicating the source of information for the associated data (activity, wastes, etc.).																		
<b>Data Type and Length</b>	CHAR (1)																		
<b>Allowed Values</b>	<table> <tr> <td>A</td><td>Part A</td></tr> <tr> <td>B</td><td>Annual/Biennial Report updated with Notification</td></tr> <tr> <td>E</td><td>Emergency</td></tr> <tr> <td></td><td>Indicates that the site is regulated as the result of a waste generation situation that was unforeseen, uncontrollable and short-term, and not expected to exceed 30 days.</td></tr> <tr> <td>I</td><td>Implementer</td></tr> <tr> <td>N</td><td>Notification</td></tr> <tr> <td>O</td><td>Out-of-State Handler</td></tr> <tr> <td>R</td><td>Annual/Biennial Report</td></tr> <tr> <td>T</td><td>Temporary</td></tr> </table>	A	Part A	B	Annual/Biennial Report updated with Notification	E	Emergency		Indicates that the site is regulated as the result of a waste generation situation that was unforeseen, uncontrollable and short-term, and not expected to exceed 30 days.	I	Implementer	N	Notification	O	Out-of-State Handler	R	Annual/Biennial Report	T	Temporary
A	Part A																		
B	Annual/Biennial Report updated with Notification																		
E	Emergency																		
	Indicates that the site is regulated as the result of a waste generation situation that was unforeseen, uncontrollable and short-term, and not expected to exceed 30 days.																		
I	Implementer																		
N	Notification																		
O	Out-of-State Handler																		
R	Annual/Biennial Report																		
T	Temporary																		
<b>Default Value</b>																			
<b>English Name</b>	<b>Handler Sequence Number (Primary Key)</b>																		
<b>Description</b>	Sequence number for each source record about a handler.																		
<b>Data Type and Length</b>	NUMBER (6.0)																		

---

## HOWNER\_OPERATOR2

---

**Allowed Values** 1 - 999999

**Default Value**

**English Name** Owner/Operator Sequence Number **(Primary Key)**

**Description** Sequential number used to order multiple occurrences of owners and operators.

**Data Type and Length** NUMBER (4.0)

**Allowed Values** 1 - 9999

**Default Value**

**Notes** This number will be incremented by one for each Add transaction.

**English Name** Owner/Operator Indicator

**Description** Code indicating whether the data is associated with a current or previous owner or operator. The system will allow multiple current owners and operators.

**Data Type and Length** CHAR (2)

**Allowed Values**  
CO Current owner  
CP Current operator

**Default Value**

**English Name** Owner/Operator Name

**Description** Owner Name: The name of the entity (individual, agency, corporation) having legal ownership of the physical operation. The owner name may or may not be the same as the actual site name or the operator name.

Operator Name: The name of the entity (individual, agency, corporation) that is responsible for the overall operation of the facility. The operator name may or may not be the same as the actual site name or the owner name.

**Data Type and Length** VARCHAR2 (40)

**Allowed Values** Any non-blank value

**Default Value**

## OWNER\_OPERATOR2

<b>English Name</b>	Owner/Operator Type	
<b>Description</b>	Owner Type: Code indicating the type of entity that legally owns the facility.	
<b>Data Type and Length</b>	Operator Type: Code indicating the type of entity that is responsible for the overall operation of the facility. CHAR (1)	
<b>Allowed Values</b>	C	County
	D	District
	F	Federal
	I	Indian
	M	Municipal
	O	Other
	P	Private
	S	State
<b>Default Value</b>		
<b>English Name</b>	Date Became Current	
<b>Description</b>	Date indicating when the owner/operator became current.	
<b>Data Type and Length</b>	DATE	
<b>Allowed Values</b>	Valid date in MM/DD/YYYY format	
<b>Default Value</b>		
<b>English Name</b>	Date Ended Current	
<b>Description</b>	Date indicating when the owner/operator changed to a different owner/operator.	
<b>Data Type and Length</b>	DATE	
<b>Allowed Values</b>	Valid date in MM/DD/YYYY format	
	blank	Not provided
<b>Default Value</b>	blank	
<b>Notes</b>	When entering a new owner/operator, any previous owners/operators that are no longer current should be updated to include a Date Ended Current.	
<b>English Name</b>	Owner/Operator Street 1	
<b>Description</b>	First line of the street address or post office box number of the facility owner or operator.	
<b>Data Type and Length</b>	VARCHAR2 (30)	
<b>Allowed Values</b>	Any value	
	blank	Not provided
<b>Default Value</b>	blank	

---

## OWNER\_OPERATOR2

---

<b>English Name</b>	Owner/Operator Street 2
<b>Description</b>	Second line of the street address or post office box number of the facility owner or operator.
<b>Data Type and Length</b>	VARCHAR2 (30)
<b>Allowed Values</b>	Any value blank          Not provided
<b>Default Value</b>	blank
<b>English Name</b>	Owner/Operator City
<b>Description</b>	The city or town in the address of the facility owner or operator.
<b>Data Type and Length</b>	VARCHAR2 (25)
<b>Allowed Values</b>	Any value blank          Not provided
<b>Default Value</b>	blank
<b>English Name</b>	Owner/Operator State
<b>Description</b>	The two-letter postal code for the state in the address of the facility owner or operator.
<b>Data Type and Length</b>	CHAR (2)
<b>Allowed Values</b>	Valid state postal code
<b>Default Value</b>	
<b>Notes</b>	For a list of valid state postal codes, refer to the Table Column Information Report for LU_STATE.
<b>English Name</b>	Owner/Operator Country
<b>Description</b>	The country code for the address of the facility owner or operator.
<b>Data Type and Length</b>	CHAR (2)
<b>Allowed Values</b>	For a complete list of valid country codes, refer to: <a href="http://www.bcpl.net/~j1m5path/isocodes.html">http://www.bcpl.net/~j1m5path/isocodes.html</a> .
<b>Default Value</b>	Valid country code US - United States

## HOWNER\_OPERATOR2

<b>English Name</b>	Owner/Operator Zip Code
<b>Description</b>	Zip code in the address of the owner or operator.
<b>Data Type and Length</b>	VARCHAR2 (14)
<b>Allowed Values</b>	Any value blank          Not provided
<b>Default Value</b>	blank
<b>English Name</b>	Owner/Operator Phone
<b>Description</b>	Telephone number associated with the owner or operator.
<b>Data Type and Length</b>	VARCHAR2 (15)
<b>Allowed Values</b>	Any value blank          Not provided
<b>Default Value</b>	blank
<b>Notes</b>	Telephone number can include space, parentheses and hyphen.
<b>English Name</b>	Dunn & Bradstreet Number
<b>Description</b>	Nine-digit unique identification number assigned by the Dunn & Bradstreet organization to a company that might own or operate a site. The identifier serves as linkage for commercially available information pertaining to the site.
<b>Data Type and Length</b>	VARCHAR2 (10)
<b>Allowed Values</b>	Any value blank          Not provided
<b>Default Value</b>	blank
<b>English Name</b>	Owner/Operator Street Number
<b>Description</b>	The street number from the address of the facility owner or operator.
<b>Data Type and Length</b>	VARCHAR2 (12)
<b>Allowed Values</b>	Any value blank          Not provided
<b>Default Value</b>	blank

---

## HOWNER\_OPERATOR2

---

<b>English Name</b>	User ID of Last Change
<b>Description</b>	Records the user ID of the last person to change the data.
<b>Data Type and Length</b>	VARCHAR2 (6)
<b>Allowed Values</b>	Valid user ID
<b>Default Value</b>	Current user ID

---

<b>English Name</b>	Date of Last Change
<b>Description</b>	Records the date that the data was last changed.
<b>Data Type and Length</b>	DATE
<b>Allowed Values</b>	Valid date/time stamp
<b>Default Value</b>	Current date and time

---

<b>English Name</b>	Notes
<b>Description</b>	Additional information regarding the owner/operator.
<b>Data Type and Length</b>	VARCHAR2 (240)
<b>Allowed Values</b>	Any value blank            Not provided
<b>Default Value</b>	blank

**\* End of Report \***